
Subject: How to retrieve current language?
Posted by [cdoty](#) on Wed, 23 Apr 2008 17:17:37 GMT
[View Forum Message](#) <> [Reply to Message](#)

I'm using Windows XP with MUI pack installed. When I use either
GetSystemLNG() or GetCurrentLanguage(), GetLangName() returns English.

What function do I use to retrieve the current language setting?

Subject: Re: How to retrieve current language?
Posted by [mirek](#) on Thu, 24 Apr 2008 03:23:12 GMT
[View Forum Message](#) <> [Reply to Message](#)

cdoty wrote on Wed, 23 April 2008 13:17 I'm using Windows XP with MUI pack installed. When I
use either
GetSystemLNG() or GetCurrentLanguage(), GetLangName() returns English.

What function do I use to retrieve the current language setting?

GetSystemLNG should work. Maybe it does not with MUI.

Could you check the GetSystemLNG code please?

Mirek

Subject: Re: How to retrieve current language?
Posted by [cdoty](#) on Thu, 24 Apr 2008 15:43:06 GMT
[View Forum Message](#) <> [Reply to Message](#)

luzr wrote on Wed, 23 April 2008 22:23 Could you check the GetSystemLNG code please?

GetSystemLNG returns 0xF8320C for Polish and 0x112BAB3 for English.

Subject: Re: How to retrieve current language?
Posted by [mirek](#) on Sat, 26 Apr 2008 08:22:00 GMT
[View Forum Message](#) <> [Reply to Message](#)

LNGAsText(0xF8320C) = PL-PL windows-1250

LNGAsText(0x112BAB3) = EN-US windows-1252

What is wrong then?

Mirek

Subject: Re: How to retrieve current language?

Posted by [sergeynikitin](#) on Wed, 07 May 2008 22:25:39 GMT

[View Forum Message](#) <> [Reply to Message](#)

I use this construction

```
String(ToLower(LNGAsText(GetCurrentLanguage()& 0xffff)))
```

This return 'en' or 'ru' in string format.
